

Image Device Information Settings

SQL Server 2016

The following table lists the device information settings for rendering in IMAGE format.

Setting	Value
Columns	The number of columns to set for the report. This value overrides the report's original settings.
ColumnSpacing	The column spacing to set for the report. This value overrides the report's original settings.
DpiX	The horizontal resolution of the output image. The default value is 96 . Applies to BMP , GIF , PNG , and TIFF output formats.
DpiY	The vertical resolution of the output image. The default value is 96 . Applies to BMP , GIF , PNG , and TIFF output formats.
EndPage	The last page of the report to render. The default value is the value for StartPage .
MarginBottom	The bottom margin value, in inches, to set for the report. You must include an integer or decimal value followed by "in" (for example, 1in). This value overrides the report's original settings.
MarginLeft	The left margin value, in inches, to set for the report. You must include an integer or decimal value followed by "in" (for example, 1in). This value overrides the report's original settings.
MarginRight	The right margin value, in inches, to set for the report. You must include an integer or decimal value followed by "in" (for example, 1in). This value overrides the report's original settings.
MarginTop	The top margin value, in inches, to set for the report. You must include an integer or decimal value followed by "in" (for example, 1in). This value overrides the report's original settings.
OutputFormat	One of the Graphics Device Interface (GDI) supported output formats: BMP , EMF , GIF , JPEG , PNG , or TIFF .
PageHeight	The page height, in inches, to set for the report. You must include an integer or decimal value followed by "in" (for example, 11in). This value overrides the report's original settings.
PageWidth	The page width, in inches, to set for the report. You must include an integer or decimal value followed by "in" (for example, 8.5in). This value overrides the report's original settings.
PrintDpiX	The horizontal resolution of the output image. The default value is 300 . Applies to the Enhanced MetaFile (EMF) output format.

PrintDpiY	The vertical resolution of the output image. The default value is 300 . Applies to the Enhanced MetaFile (EMF) output format.
StartPage	The first page of the report to render. A value of 0 indicates that all pages are rendered. The default value is 1 .

See Also

[Render](#)

[Passing Device Information Settings to Rendering Extensions](#)

[Customize Rendering Extension Parameters in RSReportServer.Config](#)

[Technical Reference \(SSRS\)](#)

Community Additions
